# WIFI Socket 数据接口

## 通信接口方案:

- UDP:
  - 路由器模式
  - 独立模式

Router	Doraemon
Password	Doraemon
STA	Doraemon
Password	Doraemon
BroadcastPort	10000
SinglePort	10001

## 设备发现接口【OK】:

BroadcastPort、SinglePort均有效。

- 获取设备列表:
  - Request

```
{
    "Cmd" : "GetDeviceList"
}\r\n
```

■ Response

## 开关控制接口【OK】:

● 获取开关状态

```
■ Request
```

```
{
    "Cmd" : "GetSwitchState"
}\r\n
```

#### Response

```
{
    "Status" : 0,
    "SwitchState" : false
}\r\n
```

● 设置开关状态

#### ■ Request

```
{
    "Cmd" : "SetSwitchState",
    "SwitchState" : false
}\r\n
```

```
{
    "Status" : 0
}\r\n
```

## 定时任务接口【OK】:

#### 【可以建立多个定时任务】

- 获取定时任务
  - Request

```
{
    "Cmd" : "GetTimingTaskList"
}\r\n
```

Response

```
"Status": 0,
   "TimingTaskList":[
          "Id": 1,
          "Running": true,
          "Open" : {
              "DateTime" : {
                 "Hour": 0,
                 "Minute" : 0
              "SwitchState" : "true"
          },
"Close" : {
              "DateTime" : {
                 "Hour": 0,
                 "Minute": 59
              "SwitchState": "false"
          },
"Loop" : {
              "Type": true,
              "Day": [ "Monday", "Tuesday", "Wednesday", "Thursday", "Friday" ]
  ]
}\r\n
```

#### ● 新建定时任务

■ Request

Response

```
{
    "Status" : 0,
    "Id" : 1
}\r\n
```

● 启动定时任务

■ Request

```
{
    "Cmd" : "RunTimingTask",
    "Id" : 1
}\r\n
```

■ Response

```
{
    "Status" : 0
}\r\n
```

● 停止定时任务

■ Request

```
{
    "Cmd" : "StopTimingTask",
    "Id" : 1
}\r\n
```

■ Response

```
{
    "Status" : 0
}\r\n
```

● 删除定时任务

■ Request

```
{
    "Cmd" : "DeleteTimingTask",
    "Id" : 1
}\r\n
```

```
{
    "Status" : 0
}\r\n
```

## 倒计时接口【OK】:

只能建立一个倒计时任务。

- 获取倒计时任务
  - Request

```
{
    "Cmd" : "GetCountDownTaskList"
}\r\n
```

■ Response

- 新建倒计时任务
  - Request

```
{
   "Cmd" : "NewCountDownTask",
   "CountDownTask" : {
      "CountDownMinute" : 60,
      "Running" : true,
      "SwitchState" : false
   }
}\r\n
```

Response

```
{
    "Status" : 0,
    "Id" : 1
}\r\n
```

- 启动倒计时任务
  - Request

```
{
    "Cmd" : "RunCountDownTask",
    "Id" : 1
}\r\n
```

```
{
    "Status" : 0
}\r\n
```

- 停止定时任务
  - Request

```
{
    "Cmd" : "StopCountDownTask",
    "Id" : 1
}\r\n
```

■ Response

```
{
    "Status" : 0
}\r\n
```

- 删除倒计时任务
  - Request

```
{
    "Cmd" : "DeleteCountDownTask",
    "Id" : 1
}\r\n
```

■ Response

```
{
    "Status" : 0
}\r\n
```

## 设备设置接口【OK】:

● 设置路由器名称&密码

```
■ Request
```

```
{
    "Cmd" : "SetRouterSettings",
    "Name" : "Doraemon",
    "Password" : "Doraemon"
}\r\n
```

#### Response

```
{
    "Status" : 0
}\r\n
```

● 设置 STA 名称&密码

#### ■ Request

```
{
    "Cmd" : "SetSTASettings",
    "Name" : "Doraemon",
    "Password" : "Doraemon"
}\r\n
```

#### Response

```
{
    "Status" : 0
}\r\n
```

● 设置设备名称

#### ■ Request

```
{
    "Cmd" : "SetDeviceName",
    "DeviceName" : "智能插座"
}\r\n
```

```
{
    "Status" : 0
}\r\n
```